

# Manual

Firmware upgrade



# Table of Contents


- 1 CONNECTION TEST .....2
- 2 UPDATING FIRMWARE .....7
- 3 DEVICE UPGRADE..... 10

These instructions will teach you how to upgrade the firmware of your Janitza measurement device using the GridVis Desktop software.


#### Content

- ▪ Checking the connection
- ▪ Selecting firmware
- ▪ Selecting a device
- ▪ Updating the firmware
- 
-


# 1 Connection test




**1** Open the **Project** tree item.




**1** Open the **Devices** tree item.




1 Open the **By Type** tree item.




1 Open the **Device type** tree item.




**1** Double click the tree entry for the device that you would like to update.




**1** Click the **communication settings** button.



1 Click the **Connection test** button.




1 Click the **OK** button.




**1** Click the **OK** button.




## 2 Updating firmware



**1** Click the **Upgrade devices** button.




**1** Click the **Choose file** button.



**1** Choose the downloaded firmware file.


A new version of the firmware is available at "[www.Janitza.de](http://www.Janitza.de)" under "Downloads".

**i**




**1** Click the **Open** button.


### 3 Device upgrade




1 Click the **Next** button.



1 Select all devices for which the firmware upgrade is to be performed.




**1** Click the **Next** button.



**1** Click the **Start update** button.

**i** The update may take a few minutes and the progress is displayed at the bottom of the GridVis



**1** Click the **Finish** button.